



FDTD Solutions

Workflow and GUI


© 2012 Lumerical Solutions, Inc.

FDTD Solutions features

- Main window
- Working with simulation objects
- Object library
- Monitor types
- Running a simulation
- Optimization and parameter sweeps
- Analysis

© 2012 Lumerical Solutions, Inc.

Main window




The graphical CAD environment is required to setup and analyze all simulations. It is also required to run all scripts.

Online Help – Layout editor

http://docs.lumerical.com/en/fdtd/ref_layout_editor.html


© 2012 Lumerical Solutions, Inc.

Showing, hiding, moving windows



© 2012 Lumerical Solutions, Inc.

Simulation objects



Object types:


- Structures
- Simulation
- Sources
- Monitors

Online Help – Simulation resources

http://docs.lumerical.com/en/ftd/ref_sim_obj.html

© 2012 Lumerical Solutions, Inc.

Structures and structure groups



Advanced objects can be obtained via the Object library

- Structure groups




Online Help – Object library

http://docs.lumerical.com/en/ftd/ref_layout_editor_object_tree.html


© 2012 Lumerical Solutions, Inc.

Structures – import options



© 2012 Lumerical Solutions, Inc.

Structures - grid attributes



Permittivity rotation


- rotate the permittivity tensor

LC orientation


- specify arbitrary orientations for the liquid crystal director

Matrix transform


- add an arbitrary unitary matrix to the dielectric tensor



Faraday Effect



Magneto-Optic Kerr Effect



LCD


Online Help – Object library

http://docs.lumerical.com/en/ftd/ref_sim_obj_attributes.html

<http://docs.lumerical.com/en/ftd/anisotropy.html>


© 2012 Lumerical Solutions, Inc.

Simulation



© 2012 Lumerical Solutions, Inc.

Sources




Online Help – Sources

http://docs.lumerical.com/en/fdtd/user_guide_source_movies.html


http://docs.lumerical.com/en/fdtd/ref_sim_obj_radiation_sources.html

© 2012 Lumerical Solutions, Inc.


Basic Sources



Dipole



Gaussian




Plane

For source movies, please visit


http://docs.lumerical.com/en/fdtd/user_guide_source_movies.html

© 2012 Lumerical Solutions, Inc.


Advanced Sources



Mode



TFSF




User-defined

For source movies, please visit

http://docs.lumerical.com/en/fdtd/user_guide_source_movies.html


© 2012 Lumerical Solutions, Inc.

Monitors and analysis groups



© 2012 Lumerical Solutions, Inc.

Object library



Advanced objects can be obtained via the Object library

- Structure groups
- Analysis groups

Online Help – Object library

http://docs.lumerical.com/en/ftdtd/ref_layout_editor_object_library.html

© 2012 Lumerical Solutions, Inc.

Monitors

FDTD Solutions has several monitors


- **Index** monitors to record material properties
- **Movie** monitors to create mpg movie files
- **Time** monitors to record electromagnetic fields as a function of time
- **Frequency** monitors to perform fourier transforms during the simulation
- **Mode expansion** monitors expand field profiles into a basis set of supported waveguide modes

© 2012 Lumerical Solutions, Inc.

Index monitors

Index Monitors record material properties

Use it to make sure you are simulating the right structure!




© 2012 Lumerical Solutions, Inc.

Movie monitors

Use **Movie Monitors** for

- visual aids in presentations!
- observe dynamic light interaction with the structure
- to develop intuition for what the simulation is doing
- to make sure the simulation is doing qualitatively what you want




© 2012 Lumerical Solutions, Inc.


Time monitors

Time Monitors record $E(t)$ and $H(t)$

- We use time monitors to
 - : Ensure the simulation has run long enough
 - : Look for resonant frequencies by doing a fast Fourier transforms (fft) of a time signal
 - Find modes of resonant cavities
 - Bandstructure calculations
- Normally data is recorded at single points



$E(t)$ from a cavity simulation



fft of above data


Online Help – PC cavity getting started example
http://docs.lumerical.com/en/fdtd/pc_micro_cavity_tutorial.html

© 2012 Lumerical Solutions, Inc.


Frequency monitors

Frequency Monitors provide frequency domain (i.e. steady state or CW) data

- : Fully vectorial CW data obtained via fourier transform of time domain fields.
- : Obtain data at many wavelengths from a single simulation! Wavelength range must be specified in advance
- : Allow us to calculate:
 - transmission, reflection, absorption, scattering, spatial field profiles, far field projections, local (near) field enhancements, light extraction enhancement



$|E|^2$ at one frequency




Power transmission(f)

Online Help – Ring resonator getting started example

http://docs.lumerical.com/en/fdtd/pc_micro_cavity_tutorial.html


© 2012 Lumerical Solutions, Inc.

Mode expansion monitors



Mode expansion monitors


expand an arbitrary field profile from a Frequency monitor using waveguide modes as a basis for the expansion



- Power coupling into waveguide modes
- S-parameter extraction to characterize components for further simulation with INTERCONNECT

© 2012 Lumerical Solutions, Inc.

Optimization and parameter sweeps



Online Help – Optimization and sweeps

http://docs.lumerical.com/en/fdtd/user_guide_run_optimization.html


http://docs.lumerical.com/en/fdtd/user_guide_run_parameter_sweep.html

© 2012 Lumerical Solutions, Inc.

Analysis of results

Browse Object tree.

Red icon means the object has simulation data




Results viewer

Right click to calculate and visualize results

© 2012 Lumerical Solutions, Inc.

Basic analysis - Visualizer



Select data to display from Attributes and Parameters sections

Export data as jpeg, text file, or copy and paste into Excel


View data in tabular format and select all or portion of data to export

Online Help – Visualizer

http://docs.lumerical.com/en/next_ftdd/ref_analysis_visualizer.html

© 2012 Lumerical Solutions, Inc.

Advanced analysis with scripting



Online Help – Scripting resources

http://docs.lumerical.com/en/ftdd/ref_scripts_scripting_language.html

http://docs.lumerical.com/en/ftdd/user_guide_scripts.html

© 2012 Lumerical Solutions, Inc.

FDTD Solutions Workflow Example



1. Create Physical Structures
2. Set Simulation Parameters
3. Define Sources
4. Define Monitors
5. Run Simulation
6. Analyze Results
7. Repeat if necessary

We will go through these steps in the following example.

© 2012 Lumerical Solutions, Inc.

Convergence testing

- Use a coarse mesh for initial simulations
 - : Memory scales as $1/dx^3$
 - : Simulation time scales as $1/dx^4$



Online Help – Testing convergence

http://docs.lumerical.com/en/fdtd/user_guide_testing_convergence.html

© 2012 Lumerical Solutions, Inc.

Simple example


Part 1: Measure the transmission through a 50 nm thick slab of Si on glass from 400 to 800nm

1. Physical Structures <ul style="list-style-type: none"> - Set drawing grid to 25nm - Create structures 	2. Simulation Area <ul style="list-style-type: none"> - Set dimension to 2D - BC (Periodic in x, PML in y) - "x span"=400nm, "y span"=1 micron - Mesh accuracy of 2
3. Sources <ul style="list-style-type: none"> - Plane wave source, from glass side to air - Wavelength 400 to 800nm 	4. Monitors <ul style="list-style-type: none"> - Movie monitor - Index monitor over entire structure - Time monitor in Si layer - Transmission/Reflection monitors "R", "T" (100 frequency points each) - Full profile over entire structure (5 frequency points)



© 2012 Lumerical Solutions, Inc.

Simple example


- Recalculate and look at the FDTD mesh
 - : Do we need a mesh override region?
- What happens at the interface?
 - : Which material is used here?
- For precise control set mesh order correctly



The interface point will be Silicon!






- Be careful to extend structure into the PML boundary condition




© 2012 Lumerical Solutions, Inc.

Simple example

- Check memory requirements! 
- Check material fits 






- Save simulation file under name **simple_example.fsp**
- Run simulation 
 - : Note when the simulation "auto-shutoff" occurs
 - Can we reduce the maximum simulation time for the next simulation?

© 2012 Lumerical Solutions, Inc.

Simple example


- Analyze results
 - : Run the movie: movie.mpg
 - : Visualize monitor results by right-clicking object in Objects Tree or selecting the object and right-clicking the result in Results View window
 - : Plot E_z vs time (auto-shutoff?)
 - : Image n and k . Is the structure correct?
 - : Plot transmission vs wavelength
 - : Image $|E_z|^2$ at 3 different wavelengths



© 2012 Lumerical Solutions, Inc.

Simple example


Part 2: Set up a parameter sweep to sweep the thickness of the Si layer from 50 nm to 100 nm over 5 points.



© 2012 Lumerical Solutions, Inc.

Simple example

- Visualize sweep results
 - Change the plot type to 1D Line plot to get transmission spectrum at a certain thickness
 - Select the Si_thickness parameter and move the slider to plot the transmission spectrum at each thicknesses



© 2012 Lumerical Solutions, Inc.

Where to find help and examples

- **Online help** at www.lumerical.com/fdtd_online_help
 - : New features summary
 - : Installation manual
 - : Getting started
 - : Reference guide
 - : Script function reference
 - : User guide
 - : Application help
- **Application summaries**
 - : www.lumerical.com/fdtd_applications

© 2012 Lumerical Solutions, Inc.

Getting help

- **Technical Support**
 - : **Email:** support@lumerical.com
 - : **Online help:** www.lumerical.com/fdtd_online_help
 - Many examples, user guide, full text search, getting started, reference guide, installation manuals
 - : Phone: +1-604-733-9006 and press 2 for support
- **Sales information:** sales@lumerical.com
- **Find an authorized sales representative for your region:**
 - : www.lumerical.com and select **Contact Us**

© 2012 Lumerical Solutions, Inc.